

SEALER APPLICATION

Tools Needed

- Wet Floor Sign
- Mop Bucket & Wringer
- Plastic Liner
- Clean, Dry Rayon Mop
- Fan (poor ventilation areas only)



Product Needed

P&G Pro Line
Floor Sealer



FREQUENCY OF CLEANING: Apply sealer on porous floors following stripping operations.


PREPARATION: Collect all tools, equipment and products required. Ensure all equipment is operational. Review MSDS, product labels and caution statements. Choose appropriate safety equipment.

SPECIAL DIRECTIONS FOR THIS TASK: Before applying sealer, make sure the floor surface is properly prepared. All residual stripper must be removed. Floor must be completely dry and tack free before performing this procedure. Start with clean, dry rayon mop. When finished, clean and return equipment to storage area. Remove wet floor sign only when surface is thoroughly dry.




STEP 1

- Put out wet floor sign in area to be mopped.



STEP 2


- Line mop bucket with plastic liner.
- Pour floor finish into mop bucket.



STEP 3

- Fully coat mop in finish.

NOTE: Start with clean, dry rayon mop.



STEP 4

- Twist lower portion of mop in wringer and wring out finish.


NOTE: Top portion of mop will feed mop right amount of finish for a thin, uniform coat.



STEP 5


- Starting at farthest point from door, picture frame a 10 ft. by 10 ft. area with mop.
- Mop inside frame using a figure-8 motion.
- Repeat Step 3 through Step 4 to replenish finish when mop head begins to drag on floor.

NOTE: Apply a thin, uniform coating.



STEP 6

- Move to next 10 ft. by 10 ft. area, working towards doorway and repeat Step 3 through Step 6.




STEP 7

- When entire area is complete, remove liner from bucket, twist, tie and discard.

NOTE: Do not pour remaining sealer back into product container.


NOTE: A second coat of sealer is not recommended and not needed in most cases. If second coat of sealer is used, allow 1.5 – 2 hours to dry before applying floor finish.



STEP 8

- Allow at least 45 minutes for floor to dry before applying finish coats.
- Floor should be tack free for 10 minutes before applying finish coats.

NOTE: For thorough drying in poor ventilation areas, dry times may be longer. A fan may be used after floor loses wet appearance (10 – 20 minutes). Direct air movement up toward ceiling or out from room.



STEP 9

- Follow the appropriate Finish Application Procedure to add finish layers.